



**General  
Mills**

**Making Food  
People Love**

# **214 Transportation Carrier Shipment Status Message**

**X12/V4010/214: 214 Transportation Carrier Shipment Status Message**

**Company:**

**General Mills**

**Modified:**

**12/16/2022**

**Notes:**

**This EDI 214 spec is used for  
General Mills Truckload and  
LTL carriers**

# Table of Contents

<b>214</b>	<b>Transportation Carrier Shipment Status Message</b>	<b>1</b>
<b>ISA</b>	<b>Interchange Control Header</b>	<b>2</b>
<b>GS</b>	<b>Functional Group Header</b>	<b>4</b>
<b>ST</b>	<b>Transaction Set Header</b>	<b>6</b>
<b>B10</b>	<b>Beginning Segment for Transportation Carrier Shipment Status Message</b>	<b>7</b>
<b>0200</b>	<b>Loop Assigned Number</b>	<b>8</b>
<b>LX</b>	<b>Assigned Number</b>	<b>9</b>
<b>0205</b>	<b>Loop Shipment Status Details</b>	<b>10</b>
<b>AT7</b>	<b>Shipment Status Details</b>	<b>11</b>
<b>MS2</b>	<b>Equipment or Container Owner and Type</b>	<b>14</b>
<b>L11</b>	<b>Business Instructions and Reference Number</b>	<b>15</b>
<b>SE</b>	<b>Transaction Set Trailer</b>	<b>16</b>
<b>GE</b>	<b>Functional Group Trailer</b>	<b>17</b>
<b>IEA</b>	<b>Interchange Control Trailer</b>	<b>18</b>

# 214 Transportation Carrier Shipment Status Message

## Functional Group=QM

**Purpose:** This Draft Standard for Trial Use contains the format and establishes the data contents of the Transportation Carrier Shipment Status Message Transaction Set (214) for use within the context of an Electronic Data Interchange (EDI) environment. This transaction set can be used by a transportation carrier to provide shippers, consignees, and their agents with the status of shipments in terms of dates, times, locations, route, identifying numbers, and conveyance.

**Not Defined:**

<u>Pos</u>	<u>Id</u>	<u>Segment Name</u>	<u>Req</u>	<u>Max Use</u>	<u>Repeat</u>	<u>Notes</u>	<u>Usage</u>
	ISA	Interchange Control Header	M	1			Must use
	GS	Functional Group Header	M	1			Must use

**Heading:**

<u>Pos</u>	<u>Id</u>	<u>Segment Name</u>	<u>Req</u>	<u>Max Use</u>	<u>Repeat</u>	<u>Notes</u>	<u>Usage</u>
010	ST	Transaction Set Header	M	1			Must use
020	B10	Beginning Segment for Transportation Carrier Shipment Status Message	M	1			Must use

<u>LOOP ID - 0200</u>			<u>999999</u>				
130	LX	Assigned Number	O	1			Must use
<u>LOOP ID - 0205</u>			<u>10</u>				
140	AT7	Shipment Status Details	O	1			Must use
146	MS2	Equipment or Container Owner and Type	O	1			Used
150	L11	Business Instructions and Reference Number	O	10			Must use
610	SE	Transaction Set Trailer	M	1			Must use

**Not Defined:**

<u>Pos</u>	<u>Id</u>	<u>Segment Name</u>	<u>Req</u>	<u>Max Use</u>	<u>Repeat</u>	<u>Notes</u>	<u>Usage</u>
	GE	Functional Group Trailer	M	1			Must use
	IEA	Interchange Control Trailer	M	1			Must use

# ISA Interchange Control Header

<b>Pos:</b>	<b>Max: 1</b>
<b>Not Defined - Mandatory</b>	
<b>Loop: N/A</b>	<b>Elements: 16</b>

**User Option (Usage):** Must use

**Purpose:** To start and identify an interchange of zero or more functional groups and interchange-related control segments

## Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
ISA01	I01	<b>Authorization Information Qualifier</b>	M	ID	2/2	Must use
<p><b>Description:</b> Code to identify the type of information in the Authorization Information  <b>All valid standard codes are used. (Total Codes: 7)</b></p>						
ISA02	I02	<b>Authorization Information</b>	M	AN	10/10	Must use
<p><b>Description:</b> Information used for additional identification or authorization of the interchange sender or the data in the interchange; the type of information is set by the Authorization Information Qualifier (I01)</p>						
ISA03	I03	<b>Security Information Qualifier</b>	M	ID	2/2	Must use
<p><b>Description:</b> Code to identify the type of information in the Security Information  <b>All valid standard codes are used. (Total Codes: 2)</b></p>						
ISA04	I04	<b>Security Information</b>	M	AN	10/10	Must use
<p><b>Description:</b> This is used for identifying the security information about the interchange sender or the data in the interchange; the type of information is set by the Security Information Qualifier (I03)</p>						
ISA05	I05	<b>Interchange ID Qualifier</b>	M	ID	2/2	Must use
<p><b>Description:</b> Qualifier to designate the system/method of code structure used to designate the sender or receiver ID element being qualified  <b>All valid standard codes are used. (Total Codes: 38)</b></p>						
ISA06	I06	<b>Interchange Sender ID</b>	M	AN	15/15	Must use
<p><b>Description:</b> Identification code published by the sender for other parties to use as the receiver ID to route data to them; the sender always codes this value in the sender ID element</p>						
ISA07	I05	<b>Interchange ID Qualifier</b>	M	ID	2/2	Must use
<p><b>Description:</b> Qualifier to designate the system/method of code structure used to designate the sender or receiver ID element being qualified  <b>Code List Summary (Total Codes: 38, Included: 1)</b>  <u>Code</u> <u>Name</u>                      08 UCC EDI Communications ID (Comm ID)</p>						
ISA08	I07	<b>Interchange Receiver ID</b>	M	AN	15/15	Must use
<p><b>Description:</b> Identification code published by the receiver of the data; When sending, it is used by the sender as their sending ID, thus other parties sending to them will use this as a receiving ID to route data to them  <b>General Mills Note:</b>  <i>General Mills ID = 9251190000</i></p>						
ISA09	I08	<b>Interchange Date</b>	M	DT	6/6	Must use
<p><b>Description:</b> Date of the interchange</p>						
ISA10	I09	<b>Interchange Time</b>	M	TM	4/4	Must use
<p><b>Description:</b> Time of the interchange</p>						
ISA11	I10	<b>Interchange Control Standards Identifier</b>	M	ID	1/1	Must use
<p><b>Description:</b> Code to identify the agency responsible for the control standard used by the message that is enclosed by the interchange header and trailer  <b>All valid standard codes are used. (Total Codes: 1)</b></p>						

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
ISA12	I11	<b>Interchange Control Version Number</b>	M	ID	5/5	Must use

**Description:** Code specifying the version number of the interchange control segments

**Code List Summary** (Total Codes: 14, Included: 1)

**Code Name**

00401 Draft Standards for Trial Use Approved for Publication by ASC X12 Procedures Review Board through October 1997

ISA13	I12	<b>Interchange Control Number</b>	M	N0	9/9	Must use
-------	-----	-----------------------------------	---	----	-----	----------

**Description:** A control number assigned by the interchange sender

ISA14	I13	<b>Acknowledgment Requested</b>	M	ID	1/1	Must use
-------	-----	---------------------------------	---	----	-----	----------

**Description:** Code sent by the sender to request an interchange acknowledgment (TA1)

**All valid standard codes are used. (Total Codes: 2)**

ISA15	I14	<b>Usage Indicator</b>	M	ID	1/1	Must use
-------	-----	------------------------	---	----	-----	----------

**Description:** Code to indicate whether data enclosed by this interchange envelope is test, production or information

**Code List Summary** (Total Codes: 3, Included: 1)

**Code Name**

P Production Data

ISA16	I15	<b>Component Element Separator</b>	M		1/1	Must use
-------	-----	------------------------------------	---	--	-----	----------

**Description:** Type is not applicable; the component element separator is a delimiter and not a data element; this field provides the delimiter used to separate component data elements within a composite data structure; this value must be different than the data element separator and the segment terminator

# GS Functional Group Header

<b>Pos:</b>	<b>Max: 1</b>
<b>Not Defined - Mandatory</b>	
<b>Loop: N/A</b>	<b>Elements: 8</b>

**User Option (Usage):** Must use

**Purpose:** To indicate the beginning of a functional group and to provide control information

## Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
GS01	479	<b>Functional Identifier Code</b>	M	ID	2/2	Must use
<b>Description:</b> Code identifying a group of application related transaction sets						
<b>Code List Summary</b> (Total Codes: 240, Included: 1)						
<b>Code Name</b>						
QM Transportation Carrier Shipment Status Message (214)						
GS02	142	<b>Application Sender's Code</b>	M	AN	2/15	Must use
<b>Description:</b> Code identifying party sending transmission; codes agreed to by trading partners						
GS03	124	<b>Application Receiver's Code</b>	M	AN	2/15	Must use
<b>Description:</b> Code identifying party receiving transmission; codes agreed to by trading partners						
<b>General Mills Note:</b>						
General Mills ID = 6125404455						
GS04	373	<b>Date</b>	M	DT	8/8	Must use
<b>Description:</b> Date expressed as CCYYMMDD						
GS05	337	<b>Time</b>	M	TM	4/8	Must use
<b>Description:</b> Time expressed in 24-hour clock time as follows: HHMM, or HHMMSS, or HHMMSSD, or HHMMSSDD, where H = hours (00-23), M = minutes (00-59), S = integer seconds (00-59) and DD = decimal seconds; decimal seconds are expressed as follows: D = tenths (0-9) and DD = hundredths (00-99)						
GS06	28	<b>Group Control Number</b>	M	N0	1/9	Must use
<b>Description:</b> Assigned number originated and maintained by the sender						
GS07	455	<b>Responsible Agency Code</b>	M	ID	1/2	Must use
<b>Description:</b> Code identifying the issuer of the standard; this code is used in conjunction with Data Element 480						
<b>Code List Summary</b> (Total Codes: 2, Included: 1)						
<b>Code Name</b>						
X Accredited Standards Committee X12						
GS08	480	<b>Version / Release / Industry Identifier Code</b>	M	AN	1/12	Must use
<b>Description:</b> Code indicating the version, release, subrelease, and industry identifier of the EDI standard being used, including the GS and GE segments; if code in DE455 in GS segment is X, then in DE 480 positions 1-3 are the version number; positions 4-6 are the release and subrelease, level of the version; and positions 7-12 are the industry or trade association identifiers (optionally assigned by user); if code in DE455 in GS segment is T, then other formats are allowed						
<b>Code List Summary</b> (Total Codes: 39, Included: 1)						
<b>Code Name</b>						
004010 Draft Standards Approved for Publication by ASC X12 Procedures Review Board through October 1997						

## Semantics:

- GS04 is the group date.
- GS05 is the group time.
- The data interchange control number GS06 in this header must be identical to the same data element in the associated functional group trailer, GE02.

**Comments:**

1. A functional group of related transaction sets, within the scope of X12 standards, consists of a collection of similar transaction sets enclosed by a functional group header and a functional group trailer.

# ST Transaction Set Header

<b>Pos: 010</b>	<b>Max: 1</b>
<b>Heading - Mandatory</b>	
<b>Loop: N/A</b>	<b>Elements: 2</b>

**User Option (Usage):** Must use

**Purpose:** To indicate the start of a transaction set and to assign a control number

## Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
ST01	143	<b>Transaction Set Identifier Code</b>	M	ID	3/3	Must use

**Description:** Code uniquely identifying a Transaction Set

**Code List Summary** (Total Codes: 298, Included: 1)

**Code Name**

214 Transportation Carrier Shipment Status Message

ST02	329	<b>Transaction Set Control Number</b>	M	AN	4/9	Must use
------	-----	---------------------------------------	---	----	-----	----------

**Description:** Identifying control number that must be unique within the transaction set functional group assigned by the originator for a transaction set

## Semantics:

1. The transaction set identifier (ST01) used by the translation routines of the interchange partners to select the appropriate transaction set definition (e.g., 810 selects the Invoice Transaction Set).

## General Mills Note:

*Example: ST\*214\*0001~*



# B10 Beginning Segment for Transportation Carrier Shipment Status Message

Pos: 020	Max: 1
Heading - Mandatory	
Loop: N/A	Elements: 3

**User Option (Usage):** Must use

**Purpose:** To transmit identifying numbers and other basic data relating to the transaction set

## Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
B1001	127	<b>Reference Identification</b>	X	AN	1/30	Must use
<p><b>Description:</b> Reference information as defined for a particular Transaction Set or as specified by the Reference Identification Qualifier</p> <p><b>General Mills Note:</b> <i>Carrier Reference Number</i></p>						
B1002	145	<b>Shipment Identification Number</b>	O	AN	1/30	Must use
<p><b>Description:</b> Identification number assigned to the shipment by the shipper that uniquely identifies the shipment from origin to ultimate destination and is not subject to modification; (Does not contain blanks or special characters)</p> <p><b>General Mills Note:</b> <i>General Mills 10-digit Shipment Number (from B204 of EDI 204 Load Tender).</i></p>						
B1003	140	<b>Standard Carrier Alpha Code</b>	M	ID	2/4	Must use
<p><b>Description:</b> Standard Carrier Alpha Code</p> <p><b>General Mills Note:</b> <i>Carrier of Record SCAC</i></p>						

## Syntax Rules:

1. R0106 - At least one of B1001 or B1006 is required.
2. E0105 - Only one of B1001 or B1005 may be present.
3. P0506 - If either B1005 or B1006 is present, then the other is required.

## Semantics:

1. B1001 is the carrier assigned reference number.
2. B1007 indicates if the reference numbers included in this transmission were transmitted to the carrier via EDI or key entered by the carrier. A "Y" indicates that the carrier received the reference numbers in an EDI transmission; an "N" indicates that the carrier did not receive the reference numbers in an EDI transmission and key entered the data from a shipper supplied document.

## Comments:

1. B1001 is the carrier's PRO (invoice number) that identifies the shipment.
2. B1003 is required when used in Transaction Set 214.
3. B1006 is the carrier assigned bar code identification or another carrier assigned shipment identification, such as a manifest number.

## General Mills Note:

*Example: B10\*8B75004\*0086500000\*SCAC~*

# Loop Assigned Number

Pos: 130      Repeat: 999999  
 Mandatory  
 Loop: 0200      Elements: N/A

**User Option (Usage):** Used

**Purpose:** To reference a line number in a transaction set

## Loop Summary:

<u>Pos</u>	<u>Id</u>	<u>Segment Name</u>	<u>Req</u>	<u>Max Use</u>	<u>Repeat</u>	<u>Usage</u>
130	LX	Assigned Number	O	1		Must use
140		Loop 0205	O		10	Used
150	L11	Business Instructions and Reference Number	O	10		Must use

# LX Assigned Number

Pos: 130	Max: 1
Heading - Optional	
Loop: 0200	Elements: 1

**User Option (Usage):** Must use

**Purpose:** To reference a line number in a transaction set

## Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
LX01	554	Assigned Number	M	N0	1/6	Must use

**Description:** Number assigned for differentiation within a transaction set

## General Mills Note:

*Example: LX\*1~*

# Loop Shipment Status Details

Pos: 140	Repeat: 10
Optional	
Loop: 0205	Elements: N/A

**User Option (Usage):** Used

**Purpose:** To specify the status of a shipment, the reason for that status, the date and time of the status and the date and time of any appointments scheduled.

## Loop Summary:

<u>Pos</u>	<u>Id</u>	<u>Segment Name</u>	<u>Req</u>	<u>Max Use</u>	<u>Repeat</u>	<u>Usage</u>
140	AT7	Shipment Status Details	O	1		Must use
146	MS2	Equipment or Container Owner and Type	O	1		Used

# AT7 Shipment Status Details

Pos: 140	Max: 1
Heading - Optional	
Loop: 0205	Elements: 7

**User Option (Usage):** Must use

**Purpose:** To specify the status of a shipment, the reason for that status, the date and time of the status and the date and time of any appointments scheduled.

## Element Summary:

Ref	Id	Element Name	Req	Type	Min/Max	Usage
AT701	1650	Shipment Status Code	X	ID	2/2	Used

**Description:** Code indicating the status of a shipment

**General Mills Note:**

Do not send Appointment Status Codes (AA/AB) in this element (see AT703 element)

**Code List Summary** (Total Codes: 42, Included: 6)

**Code Name**

AI Shipment has been Reconsigned

**General Mills Note:**

Carrier of Execution notification.

This status requires an associated MS2 segment w/Carrier of Execution SCAC.

Time sent with this status represents the time of communication to General Mills.

CP Completed Loading at Pick-up Location

D1 Completed Unloading at Delivery Location

SD Shipment Delayed

**General Mills Note:**

Send new ETA and reason code as soon as it is known that scheduled appt will not be met.

Same reason code should be sent with the new scheduled appointment status.

**Note:** The only reason codes allowed with SD status [in AT702] are AF, AG, AH, AI, AJ, AL, AM, AO, BE, D2, RC. Any other Reason Code sent [in AT702] with SD status will reject back to the carrier.

X1 Arrived at Delivery Location

**General Mills Note:**

Send Reason Code **NS** in AT702 with this status if you arrived on time for Original Scheduled Appointment

If you did not arrive on time for your Original Scheduled Appointment, one of the codes listed under the AT702 should be used.

X3 Arrived at Pick-up Location

AT702	1651	Shipment Status or Appointment Reason Code	X	ID	2/2	Used
-------	------	--	---	----	-----	------

**Description:** Code indicating the reason a shipment status or appointment reason was transmitted

**General Mills Note:**

Use a code from the list below to convey reason for missing your original appointment. If no code below accurately reflects the situation, then use any EDI compliant code.

**!! IMPORTANT NOTE REGARDING STATUS SD (SHIP DELAY)**

ONLY codes AF, AG, AH, AI, AJ, AL, AM, AO, BE, D2, RC are allowed with Ship Delay Status (SD). Any other Reason Code sent with Status SD will reject back to the carrier.

**Code List Summary** (Total Codes: 86, Included: 12)

**Code Name**

AG Consignee Related

AH Driver Related

AI Mechanical Breakdown

AJ Other Carrier Related

AL Previous Stop

AM Shipper Related

AO Weather or Natural Disaster Related

**Code Name**

BE Road Conditions  
 BO Railroad Failed to Meet Schedule  
 D2 Driver Not Available  
 NS Normal Status  
 RC Reconsigned

AT703 1652 **Shipment Appointment Status Code** X ID 2/2 Used

**Description:** Code indicating the status of an appointment to pick-up or deliver a shipment

**Code List Summary** (Total Codes: 9, Included: 2)

**Code Name**

AA Pick-up Appointment Date and/or Time  
 AB Delivery Appointment Date and/or Time

AT704 1651 **Shipment Status or Appointment Reason Code** X ID 2/2 Used

**Description:** Code indicating the reason a shipment status or appointment reason was transmitted

**General Mills Note:**

*Send code that best represents the reason for the appointment date/time*

**All valid standard codes are used. (Total Codes: 86)**

AT705 373 **Date** X DT 8/8 Must use

**Description:** Date expressed as CCYYMMDD

**General Mills Note:**

*Date of Status being reported*

AT706 337 **Time** X TM 4/8 Must use

**Description:** Time expressed in 24-hour clock time as follows: HHMM, or HHMMSS, or HHMMSSD, or HHMMSSDD, where H = hours (00-23), M = minutes (00-59), S = integer seconds (00-59) and DD = decimal seconds; decimal seconds are expressed as follows: D = tenths (0-9) and DD = hundredths (00-99)

**General Mills Note:**

*Time of Status being reported*

AT707 623 **Time Code** O ID 2/2 Must use

**Description:** Code identifying the time. In accordance with International Standards Organization standard 8601, time can be specified by a + or - and an indication in hours in relation to Universal Time Coordinate (UTC) time; since + is a restricted character, + and - are substituted by P and M in the codes that follow

**General Mills Note:**

*"LT" IS NOT A VALID TIME ZONE for General Mills.*

**Code List Summary** (Total Codes: 51, Included: 5)

**Code Name**

AT Alaska Time  
 CT Central Time  
 ET Eastern Time  
 MT Mountain Time  
 PT Pacific Time

**Syntax Rules:**

1. E0103 - Only one of AT701 or AT703 may be present.
2. P0102 - If either AT701 or AT702 is present, then the other is required.
3. P0304 - If either AT703 or AT704 is present, then the other is required.
4. C0605 - If AT706 is present, then AT705 is required.
5. C0706 - If AT707 is present, then AT706 is required.

**Semantics:**

1. If AT701 is present, AT705 is the date the status occurred. If AT703 is present, AT705 is a date related to an appointment.
2. If AT701 is present, AT706 is the time of the status. If AT703 is present, AT706 is the time of the appointment.
3. If AT707 is not present then AT706 represents local time of the status.

**General Mills Note:**

*GMI Shipments are not considered "reported" until each Delivery/Order number on the shipment has the following statuses reported successfully: AA, X3, CP (pickup statuses), AB, X1, D1 (delivery statuses).*

*Example: AT7\*X1\*NS\*\*\*20220915\*2208\*PT~*

# MS2 Equipment or Container Owner and Type

Pos: 146	Max: 1
Heading - Optional	
Loop: 0205	Elements: 2

**User Option (Usage):** Used

**Purpose:** To specify the owner, the identification number assigned by that owner, and the type of equipment

## Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
MS201	140	Standard Carrier Alpha Code	X	ID	2/4	Used

**Description:** Standard Carrier Alpha Code

**General Mills Note:**

*Carrier of Execution SCAC*

MS202	207	Equipment Number	X	AN	1/10	Used
-------	-----	------------------	---	----	------	------

**Description:** Sequencing or serial part of an equipment unit's identifying number (pure numeric form for equipment number is preferred)

**General Mills Note:**

*Carrier of Execution Equipment Number, if known. If unknown, send "NONE".*

## Syntax Rules:

1. P0102 - If either MS201 or MS202 is present, then the other is required.
2. C0402 - If MS204 is present, then MS202 is required.

## Comments:

1. MS203 identifies the type for the equipment specified in MS202.

## General Mills Note:

*This segment is required when AT701 = AI. It is not required (or mapped) when AT701 is any other status.*

*Example: MS2\*SCAC\*667585~*



# L11 Business Instructions and Reference Number

<b>Pos:</b> 150	<b>Max:</b> 10
<b>Heading - Optional</b>	
<b>Loop:</b> 0200	<b>Elements:</b> 2

**User Option (Usage):** Must use

**Purpose:** To specify instructions in this business relationship or a reference number

## Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
L1101	127	Reference Identification	X	AN	1/30	Must use

**Description:** Reference information as defined for a particular Transaction Set or as specified by the Reference Identification Qualifier

**General Mills Note:**

*GMI Order Number or Delivery Number (Send proper qualifier in L1102)*

L1102	128	Reference Identification Qualifier	X	ID	2/3	Must use
-------	-----	------------------------------------	---	----	-----	----------

**Description:** Code qualifying the Reference Identification

**Code List Summary** (Total Codes: 1503, Included: 2)

**Code Name**

CR Customer Reference Number

**General Mills Note:**

*General Mills Order Number*

DO Delivery Order Number

**General Mills Note:**

*General Mills Delivery Number*

## Syntax Rules:

1. R0103 - At least one of L1101 or L1103 is required.
2. P0102 - If either L1101 or L1102 is present, then the other is required.

## General Mills Note:

*Only one L11 is allowed per LX loop.*

*When multiple deliveries exist at a single stop, send separate LX loop for each delivery.*

*Example: L11\*2093318999\*DO~*

# SE Transaction Set Trailer

<b>Pos: 610</b>	<b>Max: 1</b>
<b>Heading - Mandatory</b>	
<b>Loop: N/A</b>	<b>Elements: 2</b>

**User Option (Usage):** Must use

**Purpose:** To indicate the end of the transaction set and provide the count of the transmitted segments (including the beginning (ST) and ending (SE) segments)

## Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
SE01	96	<b>Number of Included Segments</b>	M	N0	1/10	Must use
<b>Description:</b> Total number of segments included in a transaction set including ST and SE segments						
SE02	329	<b>Transaction Set Control Number</b>	M	AN	4/9	Must use
<b>Description:</b> Identifying control number that must be unique within the transaction set functional group assigned by the originator for a transaction set						

## Comments:

- SE is the last segment of each transaction set.

## General Mills Note:

*Example: SE\*6\*0001~*

# GE Functional Group Trailer

<b>Pos:</b>	<b>Max: 1</b>
<b>Not Defined - Mandatory</b>	
<b>Loop: N/A</b>	<b>Elements: 2</b>

**User Option (Usage):** Must use

**Purpose:** To indicate the end of a functional group and to provide control information

## Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
GE01	97	<b>Number of Transaction Sets Included</b>	M	N0	1/6	Must use
<b>Description:</b> Total number of transaction sets included in the functional group or interchange (transmission) group terminated by the trailer containing this data element						
GE02	28	<b>Group Control Number</b>	M	N0	1/9	Must use
<b>Description:</b> Assigned number originated and maintained by the sender						

## Semantics:

1. The data interchange control number GE02 in this trailer must be identical to the same data element in the associated functional group header, GS06.

## Comments:

1. The use of identical data interchange control numbers in the associated functional group header and trailer is designed to maximize functional group integrity. The control number is the same as that used in the corresponding header.

# IEA Interchange Control Trailer

Pos:	Max: 1
Not Defined - Mandatory	
Loop: N/A	Elements: 2

**User Option (Usage):** Must use

**Purpose:** To define the end of an interchange of zero or more functional groups and interchange-related control segments

## Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
IEA01	I16	<b>Number of Included Functional Groups</b>	M	N0	1/5	Must use
<b>Description:</b> A count of the number of functional groups included in an interchange						
IEA02	I12	<b>Interchange Control Number</b>	M	N0	9/9	Must use
<b>Description:</b> A control number assigned by the interchange sender						